

<b>Electric Transmission Tax (TB)</b>			
<b>Pipe " " Delimited File Layout</b>			
<b>Field Number</b>	<b>Field Name</b>	<b>Field Type</b>	<b>Description</b>
1	Year	String	Four Digit Year
2	File Type	String	Value should be "TB". Determines the type of the file
3	County Number	String	Two Digit County Code
4	County Name	String	Name of the County where the transmission originated.
5	City Name	String	Name of city where the transmission originated*
6	Township Number	Numeric	Township number in PLSS legal description where transmission originated**
7	Township name	String	Name of the Township where the transmission originated*
8	Range Number	Numeric	Range number in PLSS legal description where transmission originated **
9	Section Number	Numeric	Section number in PLSS legal description where transmission originated **
10	School District	String	School District where transmission originated
11	Fire District	String	Fire District where transmission originated
12	Other Tax District	String	Other Tax District
13	Other Tax District 2	String	Other Tax District
14	Year in Service	String	Four digit year. Year the Transmission line became active if after 1/1/2009. If prior to 1/1/2009 enter 1900. All cells must contain a four digit year.
15	Line Voltage (kv)	Decimal	Kilovolts in numeric form. May contain decimal. ***
16	Schedule Number	Numeric	Numeric value to determine the TB schedule being uploaded
17	Less than 50 kv	Decimal	Mileage of line less than 50 kilovolts.****
18	50 kv – 99 kv	Decimal	Mileage of line between 50 kilovolts and 99 kilovolts.****
19	100 kv – 199 kv	Decimal	Mileage of line between 100 kilovolts and 199 kilovolts.****
20	200 kv – 229 kv	Decimal	Mileage of line between 200 kilovolts and 229 kilovolts.****
21	200 kv – 299 kv	Decimal	Mileage of line between 200 kilovolts and 299 kilovolts.****
22	230 kv or more	Decimal	Mileage of line 230 kilovolts or greater.****
23	300 kv or more	Decimal	Mileage of line 300 kilovolts or greater.****

\* Either a Township Name or a City Name can be used per record. Using both a township and city on a record will not be allowed.

\*\*Only numbers will be allowed on these fields.

\*\*\*Kilovolts field. **NUMERIC VALUES ONLY.** Do not enter dollar signs. Commas are ok and only accept one (1) decimal point. Negative values must start with the Hyphen "-".

\*\*\*Mileage fields. **NUMERIC VALUES ONLY. RECORD ONE CIRCUIT/LINE PER ROW.** (69/115 will not be accepted.) **MAY ONLY ENTER MILEAGE FOR ONE KILOVOLT LINE PER ROW.** Commas are ok and six (6) decimal points are accepted. Negative values must start with the Hyphen "-".